

## Appendix B – Exercise Solutions (Example Code)

This appendix contains examples of code that provide solutions to each of the exercises.

- ① *Local variables have been used to shorten lines to avoid “word wrap” and improve clarity. Look for the definition of these variables within the examples and where/how they are used.*

### Appendix B1 - Example c2ex1.pmlfrm

```
--
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
--
-- File:          c2ex1.pmlfrm
--
-- Description:
--   Example form solution to Exercise 1
--
--   Supplied to support AVEVA training course TM1881 - PML: Form Design
--
-----
-- Form definition
-----

setup form !!c2ex1 dialog resizable

-- Set the form title and the initialisation call
!this.formTitle = |Example Form - Exercise 1|
!this.initcall  = |!this.init()|

-- Set the default path for gadget layout
path down

-- Input frame (LHS)
frame .inputFrame |Inputs| at x 0 anchor T+L+B

-- Top Frame - Temperature Input
frame .tempInputFrame |Temperature conversion (Input)| at x 1
  text .tempInput |Temperature| call |!this.temperatureConvert()| width 10 is REAL
  frame .tempChoiceFrame panel at xmax.tempInput ymin.tempInputFrame + 0.5
    rToggle .celsius |°C| tagwid 3 at xmax.tempInput + 3 ymin.tempInput
    rToggle .fahrenheit |°F| tagwid 3 at xmax.celsius ymin.tempInput
  exit
exit

-- Middle Frame - Temperature Range
frame .tempRangeFrame |Temperature Range| at x 1 width.tempInputFrame
  text .minimum |Minimum| | call |!this.check(1)| at x 1 width 10 is REAL
  text .maximum |Maximum| | call |!this.check(2)| at x 1 width 10 is REAL
  !format = |format !!INTEGERFMT|
  text .step |Step Size| | call |!this.check(0)| at x 1 width 10 is REAL $!format
  !bPos = |xmax.step + 1 ymin.step|
  button .fillFahrenheit linklabel |Fill with °F to °C >>| at $!bPos wid 12
  !bPos = |xmin.fillFahrenheit ymin.fillFahrenheit - size|
  button .fillCelsius linklabel |Fill with °C to °F >>| at $!bPos wid 12
exit

-- Lower Frame - Temperature Split
frame .stringSplitFrame |Temperture Split| anchor L+B+R at x 1 width.tempInputFrame
  text .stringInput |Input| | width 24 is STRING
  text .delimiter |Delimiter| | width 10 is STRING
  !bPos = |xmax.delimiter + 1 ymin.delimiter|
  button .split linklabel |Split temperature >>| at $!bPos wid 12
exit
exit

--(Continues on next page)
```

Fix1: U not valid

Fix2: REAL with one L

```

-- Results Frame (RHS)
frame .results |Results| at xmax + 1 y 0 anchor ALL

-- Top frame - Temperature output
!fSize = |width.tempInputFrame height.tempInputFrame|
frame .tempOutputFrame |Temperature conversion (Output)| anchor L+T+R at x 1 $!fSize
text .tempOutput |Temperature| call || width 10 is REAL
para .unit at xmax.tempOutput ymin.tempInput text || width 5
exit

-- Middle frame - Temperature results
!fSize = |width.tempRangeFrame height.tempRangeFrame|
frame .tempRangeOutFrame |Temperature Results| anchor L+T+R at x1 $!fSize
list .tempList dock fill width 1 height 1
exit

-- Lower frame - Split temperature
!fPos = |x1 ymin.stringSplitFrame|
!fSize = |width.stringSplitFrame height.stringSplitFrame|
frame .stringSplitOutFrame |Temperature Split Result| anchor L+B+R at $!fPos $!fSize
text .number |No. of Temp| width 10 is REAL format !!INTEGERFMT
text .result |Result | width.stringInput is STRING
exit
exit
exit

-- Constructor Method - Set the callbacks on the form
define method .c2ex1()
!this.tempChoiceFrame.callback = |!this.temperatureConvert()|
!this.fillFahrenheit.callback = |!this.fill('Fahrenheit')|
!this.fillCelsius.callback = |!this.fill('Celsius')|
!this.split.callback = |!this.split()|
endmethod

-- Initialisation Method - Set the initial gadget values and run the methods
define method .init()
!this.tempInput.val = 0
!this.tempChoiceFrame.val = 1
!this.minimum.val = 0
!this.maximum.val = 100
!this.step.val = 25
!this.stringInput.val = |10°C/30°C/20°C/5°C|
!this.delimiter.val = | / |
!this.temperatureConvert()
!this.fill(|Celsius|)
!this.split()
endmethod

-- Method .celsiusToFahrenheit(REAL)REAL - Convert the number to Fahrenheit
define method .celsiusToFahrenheit(!celsius is REAL) is REAL
!fahrenheit = !celsius * 1.8 + 32
return !fahrenheit
endmethod

-- Method .fahrenheitToCelsius(REAL)REAL - Convert the number to Celsius
define method .fahrenheitToCelsius(!fahrenheit is REAL) is REAL
!celsius = (!fahrenheit - 32) / 1.8
return !celsius
endmethod

-- Method .temperatureConvert() - Convert input temperature based on radio button
define method .temperatureConvert()
if !this.tempChoiceFrame.val.eq(1) then
!this.tempOutput.val = !this.CelsiusToFahrenheit(!this.tempInput.val)
!this.unit.val = |°F|
elseif !this.tempChoiceFrame.val.eq(2) then
!this.tempOutput.val = !this.FahrenheitToCelsius(!this.tempInput.val)
!this.unit.val = |°C|
endif
endmethod

```

Fix3: Width+height at the end of

Fix4: Incorrect constructor name

A new init method applies default values to the form

Fix5: F and C the wrong way around

--(Continues on next page)

```

-----
-- Method .fill(String) - Fill the temperature conversion list based on argument --
-----
define method .fill(!whichTemperature is STRING)
  !n = 0
  -- Loop through the supplied values and build array for the list
  do !temperature from !this.minimum.val to !this.maximum.val by !this.step.val
    !n = !n + 1
    !tempArray[!n][1] = !n.string()
    !tempArray[!n][2] = !temperature.string()
    !tempArray[!n][3] = |=|
    if !whichTemperature.eq(|Celsius|) then
      !fahrenheit = !this.celsiusToFahrenheit(!temperature)
      !tempArray[!n][4] = STRING(!fahrenheit,!!realFMT)
    else
      !celsius = !this.fahrenheitToCelsius(!temperature)
      !tempArray[!n][4] = STRING(!celsius,!!realFMT)
    endif
  enddo

  -- Set the list headings based on the argument
  if !whichTemperature.eq(|Celsius|) then
    !headings = |No. Celsius = Fahrenheit|
  else
    !headings = |No. Fahrenheit = Celsius|
  endif
  -- Display the collected data
  !this.tempList.setHeadings(!headings.split())
  !this.tempList.setRows(!tempArray)
endmethod

-----
-- Method .check(REAL) - Based on the type of check, ensure the entered values are ok --
-----
define method .check(!flag is REAL)

  -- Check the step value, if = 0 - then make it 1
  if !flag.eq(0) then
    if !this.step.val.eq(0) then
      !this.step.val = 1
    endif

  -- For others....
  elseif !flag.eq(1).or(!flag.eq(2)) then
    -- Check that text boxes have values entered in them
    if !this.maximum.val.unset() then
      !this.maximum.val = !this.minimum.val + !this.step.val
    elseif !this.minimum.val.unset() then
      !this.minimum.val = !this.maximum.val - !this.step.val
    endif
    -- Check that the values aren't lower than absolute zero.
    if (!this.minimum.val.lt(-273)) then
      !this.minimum.val = -273
      if (!this.maximum.val.leq(!this.minimum.val)) then
        !this.maximum.val = -272
      endif
    elseif (!this.maximum.val.lt(-273)) then
      !this.minimum.val = -273
      !this.maximum.val = -272
    endif
    -- Check that the maximum value is larger than the minimum value
    if (!this.maximum.val.leq(!this.minimum.val)) then
      if !flag.eq(1) then
        !this.maximum.val = !this.minimum.val + !this.step.val
      elseif !flag.eq(2) then
        !this.minimum.val = !this.maximum.val - !this.step.val
      endif
    endif
  endif
endmethod

--(Continues on next page)

```

```

-----
-- Method .split() - Split the user entered string, convert and concatenate --
-----
define method .split()
  -- Split the string
  !split = !this.stringInput.val.trim().split(!this.delimiter.val)
  !this.number.val = !split.size()
  !result = ||
  -- Loop through the split
  do !n index !split
    -- If it's Celsius....convert to Fahrenheit
    if !split[!n].substring(!split[!n].length().upcase().eq(|C|) then
      !temp = !split[!n].substring(1, !split[!n].length() - 2).real()
      !result = !result & !this.celsiusToFahrenheit(!temp).string(!INTEGERFMT) & |°F |
    else
      !temp = !split[!n].substring(1, !split[!n].length() - 2).real()
      !result = !result & !this.fahrenheitToCelsius(!temp).string(!INTEGERFMT) & |°C |
    endif
  enddo
  -- Return the concatenated string back to the form
  !this.result.val = !result
endmethod
-----
-- End of Form definition and methods --
-----
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited --
-----

```

New method to split the string

Copia para EEAA

## Appendix B2 - Example c2ex2.pmlfrm

```
--
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
--
-- File:          c2ex2.pmlfrm
--
-- Description:
--   Example form solution to Exercise 2
--
--   Supplied to support AVEVA training course TM1881 - PML: Form Design
--
-----
-- Form definition
-----

setup form !!c2ex2 dialog resizable

-- Set the form title and the initialisation call
!this.formTitle = |Example Form - Exercise 2|
!this.initcall = |!this.init()|
-- Set the default path for gadget layout
path down
frame .tabset TABSET anchor all

-- Input frame (LHS)
frame .inputFrame |Inputs| at x 0 y 0 anchor all

-- Top Frame - Temperature Input
frame .tempInputFrame |Temperature conversion (Input)| at x 1
text .tempInput |Temperature| call |!this.temperatureConvert()| width 10 is REAL
frame .tempChoiceFrame panel at xmax.tempInput ymin.tempInputFrame
  rToggle .celsius |°C| tagwid 3 at xmax.tempInput + 3 ymin.tempInput
  rToggle .fahrenheit |°F| tagwid 3 at xmax.celsius ymin.tempInput
exit
exit

-- Middle Frame - Temperature Range
frame .tempRangeFrame |Temperature Range| at x 1 width.tempInputFrame
text .minimum |Minimum| call |!this.check(1)| at x 1 width 10 is REAL
text .maximum |Maximum| call |!this.check(2)| at x 1 width 10 is REAL

!format = |format !!INTEGERFMT|
text .step |Step Size| call |!this.check(0)| at x 1 width 10 is REAL $!format
!bPos = |xmax.step + 1 ymin.step|

button .fillFahrenheit linklabel |Fill with °F to °C >>| at $!bPos wid 12
!bPos = |xmin.fillFahrenheit ymin.fillFahrenheit - size|
button .fillCelsius linklabel |Fill with °C to °F >>| at $!bPos wid 12
exit

-- Lower Frame - Temperature Split
frame .stringSplitFrame |Temperature Split| anchor L+B+R at x 1 width.tempInputFrame
text .stringInput |Input| width 24 is STRING
text .delimiter |Delimiter| width 10 is STRING
!bPos = |xmax.delimiter + 1 ymin.delimiter|
button .split linklabel |Split temperature >>| at $!bPos wid 12
exit
exit

-- Results Frame (RHS)
frame .results |Results| at x0 y 0 anchor ALL

-- Top frame - Temperature output
!fSize = |width.tempInputFrame height.tempInputFrame|
frame .tempOutputFrame |Temperature conversion (Output)| anchor L+T+R at x 1 $!fSize
text .tempOutput |Temperature| call || width 10 is REAL
para .unit at xmax.tempOutput ymin.tempInput text || width 5
exit

-- Middle frame - Temperature results
!fSize = |width.tempRangeFrame height.tempRangeFrame|
frame .tempRangeOutFrame |Temperature Results| anchor L+T+R at x1 $!fSize
list .tempList dock fill width 1 height 1
exit

--(Continues on next page
```

Tabset addd

```

-- Lower frame - Split temperature
!fPos = |x1 ymin.stringSplitFrame|
!fSize = |width.stringSplitFrame height.stringSplitFrame|
frame .stringSplitOutFrame |Temperature Split Result| anchor L+B+R at $!fPos $!fSize
    text .number |No. of Temp| width 10 is REAL format !!INTEGERFMT
    text .result |Result | width.stringInput is STRING
exit

exit
exit

!pixmap = |pixmap width 16 height 16|
!link = |linklabel width 10|
para .paAccept at xmin.tempInputFrame ymax+0.5 anchor L+B $!pixmap
button .lkAccept |Accept changes| at xmax.paAccept+1 ymin anchor L+B $!link
button .lkDiscard |Discard changes | at xmax.tempInputFrame - size ymin anchor R+B $!link
para .paDiscard at xmin.lkDiscard - 1.5 * size ymin anchor R+B $!pixmap

-- Form member to store the form values
member .data is ARRAY

-- MENU objects to be used as context menus on the list gadget
!menu = !this.newMenu(|celsiusMenu|)
!menu.add(|Callback|, |Switch to °F = °C|, |!this.fill('Fahrenheit')|)
!menu = !this.newMenu(|fahrenheitMenu|)
!menu.add(|Callback|, |Switch to °C = °F|, |!this.fill('Celsius')|)

exit

-----
-- Constructor Method - Set the callbacks on the form
-----

define method .c2ex2()
    !this.results.callback = |!this.tabCall(|
    !this.paAccept.addPixmap(!pml.getPathName('accept.png'))
    !this.paDiscard.addPixmap(!pml.getPathName('discard.png'))
    !this.lkAccept.callback = |!this.setData(1)|
    !this.lkDiscard.callback = |!this.setData(2)|
endmethod

-----
-- Initialisation Method - Set the initial gadget values and run the methods
-----

define method .init()
    !this.tempInput.val = 0
    !this.tempChoiceFrame.val = 1
    !this.minimum.val = 0
    !this.maximum.val = 100
    !this.step.val = 25
    !this.stringInput.val = |10°C/30°C/20°C/5°C|
    !this.delimiter.val = |//|
    !this.setData(1)
endmethod

-----
-- Method .tabCall(GADGET, STRING) - Open callback on Results tab
-----

define method .tabCall(!gadget is GADGET, !type is STRING)
    -- If the results tab is shown, then run the form methods
    if !type.eq(|SHOWN|) then
        !this.temperatureConvert()
        !this.fill(|Celsius|)
        !this.split()
    endif
endmethod

-----
-- Method .celsiusToFahrenheit(REAL)REAL - Convert the number to Fahrenheit
-----

define method .celsiusToFahrenheit(!celsius is REAL) is REAL
    !fahrenheit = !celsius * 1.8 + 32
    return !fahrenheit
endmethod

-----
-- Method .fahrenheitToCelsius(REAL)REAL - Convert the number to Celsius
-----

define method .fahrenheitToCelsius(!fahrenheit is REAL) is REAL
    !celsius = (!fahrenheit - 32) / 1.8
    return !celsius
endmethod

--(Continues on next page)

-----
-- Method .temperatureConvert() - Convert input temperature based on radio button
-----

```

New menu objects

New Accept/Discard buttons

Open Callback on results tab

```

-----
define method .temperatureConvert()
  if !this.tempChoiceFrame.val.eq(1) then
    !this.tempOutput.val = !this.CelsiusToFahrenheit(!this.tempInput.val)
    !this.unit.val = |°F|
  elseif !this.tempChoiceFrame.val.eq(2) then
    !this.tempOutput.val = !this.FahrenheitToCelsius(!this.tempInput.val)
    !this.unit.val = |°C|
  endif
endmethod

-----
-- Method .fill(STRING) - Fill the temperature conversion list based on argument --
-----
define method .fill(!whichTemperature is STRING)
  !n = 0
  -- Loop through the supplied values and build array for the list
  do !temperature from !this.minimum.val to !this.maximum.val by !this.step.val
    !n = !n + 1
    !tempArray[!n][1] = !n.string()
    !tempArray[!n][2] = !temperature.string()
    !tempArray[!n][3] = |=|
    if !whichTemperature.eq(|Celsius|) then
      !fahrenheit = !this.celsiusToFahrenheit(!temperature)
      !tempArray[!n][4] = STRING(!fahrenheit,!!realFMT)
    else
      !celsius = !this.fahrenheitToCelsius(!temperature)
      !tempArray[!n][4] = STRING(!celsius,!!realFMT)
    endif
  enddo
  -- Set the list headings based on the argument
  if !whichTemperature.eq(|Celsius|) then
    !headings = |No. Celsius = Fahrenheit|
    !this.tempList.setPopup(!this.celsiusMenu)
  else
    !headings = |No. Fahrenheit = Celsius|
    !this.tempList.setPopup(!this.fahrenheitMenu)
  endif
  -- Display the collected data
  !this.tempList.setHeadings(!headings.split())
  !this.tempList.setRows(!tempArray)
endmethod

-----
-- Method .check(REAL) - Based on the type of check, ensure the entered values are ok --
-----
define method .check(!flag is REAL)

  -- Check the step value, if = 0 - then make it 1
  if !flag.eq(0) then
    if !this.step.val.eq(0) then
      !this.step.val = 1
    endif

  -- For others....
  elseif !flag.eq(1).or(!flag.eq(2)) then
    -- Check that text boxes have values entered in them
    if !this.maximum.val.unset() then
      !this.maximum.val = !this.minimum.val + !this.step.val
    elseif !this.minimum.val.unset() then
      !this.minimum.val = !this.maximum.val - !this.step.val
    endif
    -- Check that the values aren't lower than absolute zero.
    if (!this.minimum.val.lt(-273)) then
      !this.minimum.val = -273
      if (!this.maximum.val.leq(!this.minimum.val)) then
        !this.maximum.val = -272
      endif
    elseif (!this.maximum.val.lt(-273)) then
      !this.minimum.val = -273
      !this.maximum.val = -272
    endif
    -- Check that the maximum value is larger than the minimum value
    if (!this.maximum.val.leq(!this.minimum.val)) then
      if !flag.eq(1) then
        --(Continues on next page)

```

```

        !this.maximum.val = !this.minimum.val + !this.step.val
    elseif !flag.eq(2) then
        !this.minimum.val = !this.maximum.val - !this.step.val
    endif
endif
endif
endmethod

-----
-- Method .split() - Split the user entered string, convert and concatenate --
-----

define method .split()
    -- Split the string
    !split = !this.stringInput.val.trim().split(!this.delimiter.val)
    !this.number.val = !split.size()
    !result = ""
    -- Loop through the split
    do !n index !split
        -- If it's Celsius...convert to Fahrenheit
        if !split[!n].substring(!split[!n].length()).uppercase().eq(|C|) then
            !temp = !split[!n].substring(1, !split[!n].length() - 2).real()
            !result = !result & !this.celsiusToFahrenheit(!temp).string(!INTEGERFMT) & |°F |
        else
            !temp = !split[!n].substring(1, !split[!n].length() - 2).real()
            !result = !result & !this.fahrenheitToCelsius(!temp).string(!INTEGERFMT) & |°C |
        endif
    enddo
    -- Return the concatenated string back to the form
    !this.result.val = !result
endmethod

-----
-- Method .setData(REAL) - Store or retrieve the gadget values from the storage array --
-----

define method .setData(!flag is REAL)
    -- Either save the values, or bring them back (array of strings)
    if !flag.eq(1) then
        !this.data[1] = !this.tempInput.val
        !this.data[2] = !this.tempChoiceFrame.val
        !this.data[3] = !this.minimum.val
        !this.data[4] = !this.maximum.val
        !this.data[5] = !this.step.val
        !this.data[6] = !this.stringInput.val
        !this.data[7] = !this.delimiter.val
    else
        if !this.data.size().eq(7) then
            !this.tempInput.val = !this.data[1]
            !this.tempChoiceFrame.val = !this.data[2]
            !this.minimum.val = !this.data[3]
            !this.maximum.val = !this.data[4]
            !this.step.val = !this.data[5]
            !this.stringInput.val = !this.data[6]
            !this.delimiter.val = !this.data[7]
            !this.temperatureConvert()
            !this.fill(|Celsius|)
            !this.split()
        endif
    endif
endmethod

-----
-- End of Form definition and methods --
-----
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited --
-----

```

Method to transfer to and from the .data member



## Appendix B3 - Example c2ex3.pmlfrm

```
--
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
--
-- File: c2ex3.pmlfrm
--
-- Description:
-- Example form solution to Exercise 3
--
-- Supplied to support AVEVA training course TM1881 - PML: Form Design
--
--
-- Form definition
--
setup form !!c2ex3 dialog docking

-- Set the form title
!this.formTitle = |FILE Objects - Exercise 3|

-- Define the gadgets for the form
textpane .txtp at x 0 ymax anchor all width 60 height 15
para .para at xmin ymax anchor b+l+r text || width 30
button .load |Load| at xmax.txtp - size ymin anchor b+r pixmap width 16 height 16
button .save |Save| at xmin - size ymin anchor b+r pixmap width 16 height 16

-- Form member to record which file is being used
member .file is FILE

exit

-- Constructor Method - Set the imahes and callbacks on the form
--
define method .c2ex3()
-- Apply the images to the pixmap buttons
!this.load.addPixmap(!pml.getPathName(|openbrowser.png|))
!this.save.addPixmap(!pml.getPathName(|saveview16.png|))
-- Apply tooltips to the icon buttons for clarity
!this.load.setToolTip(|Load text file|)
!this.save.setToolTip(|Save text file|)
-- Set the callback to run the standard function !!filebrowser
!dir = 'C:\AVEVA\Plant\Training'
!this.load.callback = !!fileBrowser('|' & !dir & '|', '|', 'Load text file', $
TRUE, '!!c2ex3.load(!!fileBrowser.file)')
!this.save.callback = !!fileBrowser('|' & !dir & '|', '|', 'Save text file', $
FALSE, '!!c2ex3.save(!!fileBrowser.file)')
endmethod

-- Method .load(FILE) - Read the chosen file into the textpane
--
define method .load(!file is FILE)
-- Store and read the file
!this.file = !file
!this.txtp.val = !this.file.readFile()
-- Display the filename
!this.para.val = !this.file.string()
endmethod

-- Method .save(FILE) - Save the chosen file from the textpane
--
define method .save(!file is file)
!this.file = !file
!this.file.writeFile('OVER', !this.txtp.val)
!this.para.val = !this.file.string()
endmethod

-- End of Form definition and methods
--
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
--
```

## Appendix B4 - Example c2ex4.pmlfrm

```
--
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
--
-- File: c2ex4.pmlfrm
--
-- Description:
-- Example form solution to Exercise 4
--
-- Supplied to support AVEVA training course TM1881 - PML: Form Design
--
-----
-- Form definition
-----

setup form !!c2ex4 dialog resiz

-- Set the form title and initialisation call
!this.formTitle = |Equipment Checker|
!this.initcall = |!this.init()|

-- Create a MENU object for use as a context menu on the list gadget
!this.newMenu(|popupMenu|)
!popupCall = '!!CE = !this.nozzleList.selection().dbref()'
!this.popupMenu.add('CALLBACK', 'Go to Nozzle', !popupCall)

-- Define the gadgets at the top of the form
button .update linklabel |Update| call |!this.init()| width 5
para .title at xmax ymin anchor t+l+r text |Available Equipments below | width 34
line .line at xmin.update ymax anchor t+l+r horizontal width 42

!buttPos = |xmax - size ymax anchor b+r|
!anch1 = |anchor t+l+r |
!anch2 = |anchor b+l+r|

-- Define the gadgets to choose the equipments from
combo .equip at xmin.update ymax+0.2 |Select an Equipment| tagwidth 15 $!anch1 width 24
list .nozzleList at xmin.update ymax+0.2 anchor all width 40 length 5
button .refresh linklabel |Refresh Checks| at $!buttPos width 9.6

-- Define the gadgets to allow the attributes to be altered
!tag = |Equipment Attributes|
textpane .atta |$!tag| at xmin.nozzleList ymax-0.5 $!anch2 width 42 height 3.5
button .updateAtta linklabel |Update Attributes| at $!buttPos width 10.3

exit

-----
-- Constructor Method - Set the images and callbacks on the form
-----

define method .c2ex4()
-- Set the titles and context menu on the list
!title = |Nozzles/Connected?/Attached?/Aligned?/Size?|
!this.nozzleList.setHeadings(!title.split(|/|))
!this.nozzleList.setpopup(!this.popupMenu)
-- Pre-fill-in some attributes to be edited
!info[1] = 'Description - Unset'
!info[2] = 'Function - Unset'
!info[3] = 'Purpose - Unset'
!this.atta.val = !info
-- Set the gadget callbacks
!this.equip.callback = |!this.setEquip(|
!this.refresh.callback = |!this.checkNozzles()|
!this.updateAtta.callback = |!this.updateAtt(2)|
endmethod

-----
-- Initialisation Method - Collect all equi for level and display nozzles
-----

define method .init()
-- If at SITE level, collect for the site otherwise do it for ZONE
if !!ce.type.eq(|SITE|) then
!level = |SITE|
else
!level = |ZONE|
endif
-- (Continues on next page)
```

```

-- Collect the equipment using PML 1 style collection syntax
VAR !coll COLL ALL EQUIP FOR $!level
handle ANY
    !!alert.error(|Make sure you are at an EQUI, ZONE or SITE element|)
elsehandle NONE
    -- If no equipment are found, and we're at a ZONE try collecting for SITE
    if !coll.size().eq(0) and !level.eq(|ZONE|) then
        !!alert.message(|No equipment found in current ZONE, so whole SITE will be searched|)
        VAR !coll COLL ALL EQUIP FOR SITE
        !level = |SITE|
    endif
    -- Update the title paragraph gadget
    !this.title.val = |Available Equipments below | & !level
    -- Evaluate the fullnames of the equis and display the information
    VAR !name EVAL FLNN FOR ALL FROM !coll
    !this.equip.dtext = !name
    !this.equip.rtext = !coll
    -- Collect the nozzles
    !this.collectNozzles()
endhandle
endmethod

-----
-- Method .collectNozzles() - For the selected EQUI, collect all the nozzles --
-----

define method .collectNozzles()
    -- Get the selected EQUI element
    !equipRef = !this.equip.selection().dbref()
    if !equipRef.unset() then
        -- If the element is unset, then clear the nozzle list
        !this.nozzleList.clear()
    else
        -- Perform a PML2 style collection for the nozzles
        !nozzColl = object COLLECTION()
        !nozzColl.type('NOZZ')
        !nozzColl.scope(!equipRef)
        !results = !nozzColl.results()
        !this.nozzleList.dtext = !results.evaluate(object block ('!results[!evalIndex].flnn'))
        !this.nozzleList.rtext = !results.evaluate(object block ('!results[!evalIndex].string()'))
        -- Check the nozzles and update the results
        !this.checkNozzles()
        !this.updateAtt(1)
    endif
endmethod

-----
-- Method .setEquip(GADGET, STRING) - Open callback on combo gadget to check user entry --
-----

define method .setEquip(!gad is gadget, !event is STRING)
    -- If the user has typed into the gadget
    if !event.eq('VALIDATE') then
        !userInput = !this.equip.displayText()
        -- Loop through available equipments and choose the nearest match
        do !n index !this.equip.dtext
            !chrs = !userInput.length()
            !test = !this.equip.dtext[!n].upcase().substring(1, !chrs)
            if !userInput.upcase().eq(!test) then
                !this.equip.val = !n
                break
            endif
        enddo
    endif
    -- Recollect the nozzles on the newly selected equipment
    !this.collectNozzles()
endmethod

-----
-- Method .checkNozzles() - Check the collected nozzles and display the results --
-----

define method .checkNozzles()
    if !this.nozzleList.rtext.set() then
        -- Loop through the collected nozzles
        do !n index !this.nozzleList.rtext
            !nozz = !this.nozzleList.rtext[!n].dbref()
            -- set the default result
            do !m from 2 to 4
                !result[!m] = |N/A|
            enddo
            -- Check 1: is the connection valid
        enddo
    endif
    -- (Continues on next page)

    if !nozz.cref.unset().or(!nozz.cref.badref()) then
        !result[1] = |Check|
    endif
endmethod

```

```

else
    !result[1] = |OK|
    !end = |t|
    if !nozz.cref.href.eq(!nozz) then
        !end = |h|
    endif
    -- Check 2: is the nozzle and the same position as the attached
    if !nozz.pos.wrt( /* ).eq(!nozz.cref.attribute(!end & |pos|).wrt( /* )) then
        !result[2] = |OK|
    endif
    -- Check 3: is the nozzle and the same direction as the attached
    if !nozz.pdir[1].wrt( /* ).eq(!nozz.cref.attribute(!end & |dir|).wrt( /* )) then
        !result[3] = |OK|
    endif
    -- Check 4: is the nozzle and the same size as the attached
    if !nozz.cpar[1].eq(!nozz.cref.attribute(!end & |bore|.real())) then
        !result[4] = |OK|
    endif
    endif
    -- Record the check results for this nozzle
    !nozzleInfo[!n][1] = !nozz.flnn
    !nozzleInfo[!n].appendArray(!result)
enddo
-- Apply the results back to the list gadget
!rtext = !this.nozzleList.rtext
!this.nozzleList.setRows(!nozzleInfo)
!this.nozzleList.rtext = !rtext
endif
endmethod

-----
-- Method .updateAtt(REAL) - Check the collected nozzles and display the results --
-----

define method .updateAtt(!flag is REAL)
    -- Get the selected piece of equipment and the available attributes
    !equip = !this.equip.selection().dbref()
    !availAtts = !equip.attributes()
    -- Update the textpane title
    !this.atta.tag = !equip.flnn & ' Attributes'
    !rows = !this.atta.val
    -- Loop through the rows of the textpane to extract and use the information
    !out = ARRAY()
    do !n index !rows
        -- Split the line on a "-"
        !split = !rows[!n].split('-')
        !attrib = !split[1].trim()
        -- Evaluate the available attributes so they are the same string length as the entered
        !block = object block ('!availAtts[!evalIndex].upcase().substring(1, !attrib.length())')
        !avail = !availAtts.evaluate(!block)
        -- If the attribute can be found, then use it
        if !avail.findfirst(!attrib.upcase()).set() then
            if !flag.eq(1) then
                -- If the flag = 1 then update the textpane with the current attribute value
                !value = !equip.attribute(!availAtts[!avail.findfirst(!attrib.upcase())])
                !out.append(!attrib & | - | & !value)
            elseif !flag.eq(2) then
                -- If the flag = 2 then assign the value to the attribute
                !val = !split[2].trim()
                !equip.attribute(!availAtts[!avail.findfirst(!attrib.upcase())]).assign(!val)
                !out.append(!attrib & | - | & !val)
            endif
        endif
    enddo
    -- Display the updated attribute list
    !this.atta.val = !out
endmethod

-----
-- End of Form definition and methods --
-----
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited --
-----

```

## Appendix B5 - Example !!traExampleVolumeView

```
--
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
--
-- File: traExampleVolumeView.pmlfrm
--
-- Description:
-- Form to demonstrate an VOLUME view gadget
--
-- Supplied to support AVEVA training course TM1881 - PML: Form Design
--
--
-- Form definition
--
setup form !!traExampleVolumeView

-- Set the form title
!this.formTitle = |Volume View|

-- Set the callbacks on the form
!this.initcall = |!this.init()|
!this.firstShownCall = |!this.firstShown()|
!this.killingCall = |!this.close()|

-- Define a context menu for the volume view gadget
!this.newMenu(|pop1|)
!this.pop1.add('CALLBACK', 'Limits CE', '!this.limitsCE()')
-- Set the standard icon size
!pix = |pixmap wid 16 hei 16|

-- Define a prompt paragraph gadget. This will provide feedback to the user
para .prompt text |Navigate : | width 46 lines 1

-- Define the four buttons down the L.H.S of the form
button .but1 at xmin ymax call |!this.limitsCE()| $!pix
button .but2 at xmin ymax call |!this.walkDrawlist()| $!pix
button .but3 at xmin ymax call |!this.setDrawlist(1, FALSE)| $!pix
button .but4 at xmin ymax call |!this.setDrawlist(2, FALSE)| $!pix

-- Define the volume view element
view .volumeView at xmax.but1 ymax.prompt volume

-- Set the size and the initial viewing direction
width 45 height 15
limits auto
isometric 3

-- Set the required "INMODES". These are required if the user is to pick from the view
inmode create _navi type |DES_NAVIGATE| $* Navigate
inmode create _pick type |DES_PICK| $* Standard Element Pick
inmode create _pAny type |DES_PICK_ANY| $* Pick Any (Element, Ppoint, Pline)
inmode create _pLine type |DES_PICK_PLINE| $* Plines
inmode create _point type |DES_PICK_POINT| $* Ppoints
inmode create _screen type |DES_3D_LINE| $* Screen Position
inmode create _pickxgeom type |DES_PICK_XGEOM| $* Laser Model rays
inmode create _pickDetail type |DES_PICK_DETAIL| $* Default (Navigation)
inmode create _default type |DES_NAVIGATE| $* Default (Navigation)

exit

-- Define the footer
line .line at xmin.but1 ymax+0.5 anchor b+l+r horizontal width 47.5
para .footer at xcen - 0.5 * size ymax anchor b text |AVEVA Training| width 11

-- A form member to remember the drawlist associated with the view
member .drawlist is REAL

exit

--(Continues on next page)
```

```

-----
-- Constructor Method - Setup the form when it is loaded                                     --
-----
define method .traExampleVolumeView()

    -- Apply the icons to the four buttons
    !this.but1.addPixmap(!pml.getPathName(|autoce16.png|))
    !this.but2.addPixmap(!pml.getPathName(|ng_zoomtodrawlist.png|))
    !this.but3.addPixmap(!pml.getPathName(|addce16.png|))
    !this.but4.addPixmap(!pml.getPathName(|removece16.png|))

    -- As icons are being used, set tooltips to help users
    !this.but1.setToolTip(|Limits CE|)
    !this.but2.setToolTip(|Walk to Drawlist|)
    !this.but3.setToolTip(|Add to Drawlist|)
    !this.but4.setToolTip(|Remove from Drawlist|)

    -- Apply some default settings to the view element
    !this.volumeView.borders = FALSE
    !this.volumeView.background = |darkslate|
    !this.volumeView.shaded = TRUE
    !this.volumeView.projection = |PARALLEL|
    !this.volumeView.radius = 100
    !this.volumeView.range = 500.0
    !this.volumeView.eyemode = FALSE
    !this.volumeView.step = 25
    !this.volumeView.setpopup(!this.pop1)

    -- Set Defaults for various INMODEs
    !this.volumeView.navi.cursor      = 'Pointer'
    !this.volumeView.navi.prompt     = 'Navigate : '
    !this.volumeView.pick.cursor     = 'Pointer'
    !this.volumeView.pick.prompt     = 'Pick Element : '
    !this.volumeView.pAny.cursor     = 'Pointer'
    !this.volumeView.pAny.prompt     = 'Pick Any : '
    !this.volumeView.pLine.cursor    = 'Pointer'
    !this.volumeView.pLine.prompt    = 'Pick Pline : '
    !this.volumeView.point.cursor    = 'Pick'
    !this.volumeView.point.prompt    = 'Point Ppoint : '
    !this.volumeView.screen.cursor   = 'Crosshair'
    !this.volumeView.screen.prompt   = 'Pick 3D Position : '
    !this.volumeView.default.cursor  = 'Pointer'
    !this.volumeView.default.prompt  = 'Navigate : '

    -- Create local drawlist within the global object
    !this.drawlist = !!gphDrawlists.createDrawlist()
endmethod

-----
-- First Shown Method - Register the view gadget and attach the drawlist                     --
-----
define method .firstShown()
    -- Add 3D view to view system
    !!gphViews.add(!this.volumeView)
    -- Add local drawlist add to 3D view
    !!gphDrawlists.attachView(!this.drawlist, !this.volumeView)
endmethod

-----
-- Initialisation Method - Update the drawlist and active the view                         --
-----
define method .init()
    -- Update the drawlist
    !this.setDrawlist(1, TRUE)
    -- Active the volume view
    !this.volumeView.active = TRUE
    -- Turn on holes drawn
    !!gphDrawlists.drawlists[!this.drawlist].holes(TRUE)
endmethod

-----
-- Killing Call Method - Detach the drawlist and then delete it                           --
-----
define method .close()
    !!gphDrawlists.detachView(!this.volumeView)
    !!gphDrawlists.deleteDrawlist(!this.drawlist)
endmethod

--(Continues on next page)

```

```

-----
-- Method .walkDrawlist() - Set the view limits based on the drawlist --
-----
define method .walkDrawlist()
  -- Get the drawlist associated with the view
  !drawlist = !!gphDrawlists.drawlist(!this.drawlist)
  -- Derive a volume object from the members of the drawlist
  !volume = object volume(!drawlist.members())
  -- Derive a limits array in the expected format
  !limits[1] = !volume.from.east
  !limits[2] = !volume.to.east
  !limits[3] = !volume.from.north
  !limits[4] = !volume.to.north
  !limits[5] = !volume.from.up
  !limits[6] = !volume.to.up
  -- Apply the limits to the volume view
  !this.volumeView.limits = !limits
  handle ANY
    -- Incase the drawlist is empty or has no volume
  endhandle
endmethod

-----
-- Method .limitsCE() - Set the view limits based on the current element --
-----
define method .limitsCE()
  -- Set the Views limits based on the chosen element
  !!gphViews.limits(!this.volumeView, !!CE)
endmethod

-----
-- Method .setDrawlist(REAL, BOOLEAN) - Update the drawlist --
-----
define method .setDrawlist(!flag is REAL, !reset is BOOLEAN)
  -- Get the drawlist associated with the view
  !drawlist = !!gphDrawlists.drawlist(!this.drawlist)
  -- Clear the drawlist is a reset is requested
  if !reset then
    !drawlist.removeall()
  endif
  -- Add/Remove CE
  if !flag.eq(1) then
    !drawlist.add(!!CE)
  elseif !flag.eq(2) then
    !drawlist.remove(!!CE)
  endif
  -- Update the limits of the view based on the drawlist
  !this.walkDrawlist()
endmethod

-----
-- End of Form definition and methods --
-----
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited --
-----

```

## Appendix B6 - Example c2ex5.pmlfrm

```
--
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
--
-- File: c2ex5.pmlfrm
--
-- Description:
-- Example form solution to Exercise 5
--
-- Supplied to support AVEVA training course TM1881 - PML: Form Design
--
-----
-- Form definition
-----

setup form !!c2ex5 dialog docking

-- Set the form title and callbacks
!this.formTitle = |Equipment Checker|
!this.initcall = |!this.init()|
!this.firstShownCall = |!this.firstShown()|
!this.killingCall = |!this.close()|
!this.quitcall = |!this.clear()|

-- Create a MENU object for use as a context menu on the list gadget
!this.newMenu(|popupMenu|)
!this.popupMenu.add('CALLBACK', 'Go to Nozzle', '!!CE = !this.nozzleList.selection().dbref()')
-- Define the prompt and view gadgets
para .prompt text |Navigate : | width 46 lines 1
frame .view panel at x 0.5 ymax.prompt anchor all wid 1 hei 1
view .volumeView at x 0.5 ymax.prompt VOLUME
width 40 height 28
border off
shading on
isometric 3
exit
exit

-- Define the gadgets at the top of the form
button .update linklabel |Update| at xmax ymin.prompt anchor t+r call |!this.init()| width 5
para .title at xmax ymin anchor t+r text |Available Equipments below | width 34
line .line at xmin.update ymax anchor t+r horizontal width 42

!buttPos = |xmax - size ymax anchor b+r|
!anch1 = |anchor t+l+r |
!anch2 = |anchor b+l+r|
-- Define the gadgets to choose the equipments from
combo .equip at xmin.update ymax+0.2 |Select an Equipment| tagwidth 15 anchor t+r width 24
list .nozzleList at xmin.update ymax+0.2 anchor t+r width 40 length 5
button .refresh linklabel |Refresh Checks| at $!buttPos anchor t+r width 9.6

-- Define the gadgets to allow the attributes to be altered
!tag = |Equipment Attributes|
textpane .atta |$!tag| at xmin.nozzleList ymax-0.5 anchor t+r width 42 height 3.5
button .updateAtta linklabel |Update Attributes| at $!buttPos anchor t+r width 10.3
para .taskTitle at xmin.update ymax.atta + 0.5 anchor t+r text |Available Tasks|
line .taskLine at xmin.update ymax.taskTitle anchor t+r horiz width 42

!anch = |anchor t+r|
para .clipPix at xmin + 1 ymax.taskLine + 0.2 anchor t+r pixmap wid 16 hei 16
button .clipBut linklabel at xmax + 1 ymin |Add Connected and Enable Clipbox...| $!anch
para .tagNozzPix at xmin.clipPix ymax + 0.2 anchor t+r pixmap wid 16 hei 16
button .tagNozzBut linklabel at xmax + 1 ymin |Tag Selected Nozzle| $!anch
para .tagNozzlesPix at xmin.clipPix ymax + 0.2 anchor t+r pixmap wid 16 hei 16
button .tagNozzlesBut linklabel at xmax + 1 ymin |Tag All Nozzles| $!anch
para .hlNozzPix at xmin.clipPix ymax + 0.2 anchor t+r pixmap wid 16 hei 16
button .hlNozzBut linklabel at xmax + 1 ymin |Highlight Nozzles| $!anch

frame .limitslide foldup |Edit Clip Volume| at xmin.atta ymax.hlNozzPix + 0.5 $!anch width 41
slider .slide anchor l+r range 0 +2000 step 100 val 0 width 40 height 2.5
text .minslide at xmin.limitslide+0.2 ymin.limitslide+2.5 width 5 is REAL
text .maxslide at xmax.limitslide-size ymin.limitslide+2.5 width 5 is REAL
toggle .incl |Update view limits?| at xmax.minslide + 5 ymin.limitslide+2.5
exit

!fPos = |xmin.atta ymax.limitslide+0.1|
frame .colour foldup |Edit Highlight Colour| at $!fPos $!anch width .limitslide
para .para1 at xmin.colour + 0.5 ymin.colour + 1.2 text |Current equipment |
```



```

button .butt1 | | at xmax.para1 - 3 ymin.para1 pixmap wid 25 hei 15
para .para2    at xmin.colour + 0.5 ymax.butt1    text |Connected nozzles |
button .butt2 | | at xmax.para2 - 3 ymax.butt1 pixmap wid 25 hei 15
para .para3    at xmin.colour + 0.5 ymax.butt2    text |Unconnected nozzles|
button .butt3 | | at xmax.para3 - 3 ymax.butt2 pixmap wid 25 hei 15
para .para4    at xmin.colour + 0.5 ymax.butt3    text |Check nozzles      |
button .butt4 | | at xmax.para3 - 3 ymax.butt3 pixmap wid 25 hei 15

frame .colourpick panel at xmax.butt1 + 2.5 ymin.colour + 0.5 width 10
!val = 0
do !I from 1 to 8
  do !J from 0 to 4
    !val = !val + 1
    !no = !I & |000| & !J
    !x = (!I * 2) - 1
    !y = (!J * 0.6) + 0.75
    button .butt$!no | | pixmap at x$!x ymin.colourpick + $!y backg $!val width 10 aspect 1
    !this.butt$!<no>.callback = !|this.colourpick($!val)|
  enddo
enddo
exit
exit
member .clipbox is GPHCLIPBOX
member .drawlist is REAL
member .limits is ARRAY
member .col    is REAL
member .tagged is ARRAY
member .highlight is ARRAY
exit
-----
-- Constructor Method - Set the images and callbacks on the form --
-----
define method .c2ex5()
-- Set the titles and context menu on the list
!title = |Nozzles/Connected?/Attached?/Aligned?/Size?|
!this.nozzleList.setHeadings(!title.split(|/|))
!this.nozzleList.setpopup(!this.popupMenu)
-- Pre-fill-in some attributes to be edited
!info[1] = 'Description - Unset'
!info[2] = 'Function - Unset'
!info[3] = 'Purpose - Unset'
!this.atta.val = !info
-- Set the gadget callbacks
!this.equip.callback = !|this.setEquip(|
!this.nozzleList.callback = !|this.check(|
!this.refresh.callback = !|this.checkNozzles(|
!this.updateAtta.callback = !|this.updateAtt(2)|

!this.slide.callback = !|this.slide(|
!this.minslide.callback = !|this.updateRange(|
!this.maxslide.callback = !|this.updateRange(|

!this.butt1.callback = !|this.colourpick('A' )|
!this.butt2.callback = !|this.colourpick('B' )|
!this.butt3.callback = !|this.colourpick('C' )|
!this.butt4.callback = !|this.colourpick('D' )|

!this.clipBut callback = !|this.enableClip(|
!this.tagNozzBut .callback = !|this.tag(!this.tagNozzBut)|
!this.tagNozzlesBut.callback = !|this.tag(!this.tagNozzlesBut)|
!this.hlNozzBut .callback = !|this.highlight(|

!this.volumeView.borders = FALSE
!this.volumeView.background = |darkslate|
!this.volumeView.shaded = TRUE
!this.volumeView.projection = |PARALLEL|
!this.volumeView.radius = 100
!this.volumeView.range = 500.0
!this.volumeView.eyemode = FALSE
!this.volumeView.step = 25

!this.minslide.val = 0
!this.maxslide.val = 2000

!this.drawlist = !|gphDrawlists.createDrawList()
!this.clipPix.addPixmap(!|pml.getPathName('clipcel6.png'))
!this.tagNozzPix.AddPixmap(!|PML.GetPathName('draft_lab_01.png'))
!this.tagNozzlesPix.AddPixmap(!|PML.GetPathName('draft_lab_01.png'))
!this.hlNozzPix.AddPixmap(!|PML.GetPathName('nozzle-16.png'))

```

```

!this.colourpick.visible = FALSE
!this.limitslide.visible = FALSE
!this.limitslide.expanded = FALSE
!this.colour.visible = FALSE
!this.colour.expanded = FALSE

!this.clipbox = object GPHCLIPBOX()
!this.clipbox.view = !this.volumeView
!this.clipbox.capOn()

!this.butt1.background = 1
!this.butt2.background = 20
!this.butt3.background = 18
!this.butt4.background = 23

endmethod

-----
-- First Shown Method - Collect all equi for level and display nozzles --
-----
define method .firstShown()
  -- Add 3D view to view system
  !!gphViews.add(!this.volumeView)
  -- Add local drawlist add to 3D view
  !!gphDrawlists.attachView(!this.drawlist, !this.volumeView)
endmethod

-----
-- Killing Call Method - Collect all equi for level and display nozzles --
-----
define method .close()
  !!gphDrawlists.detachView(!this.volumeView)
  !!gphDrawlists.deleteDrawlist(!this.drawlist)
endmethod

-----
-- Initialisation Method - Collect all equi for level and display nozzles --
-----
define method .init()
  -- Activate the view for use
  !this.volumeView.active = TRUE
  -- If at SITE level, collect for the site otherwise do it for ZONE
  if !!ce.type.eq(|SITE|) then
    !level = |SITE|
  else
    !level = |ZONE|
  endif
  -- Collect the equipment using PML 1 style collection syntax
  VAR !coll COLL ALL EQUIP FOR $!level
  handle ANY
    !!alert.error(|Make sure you are at an EQUI, ZONE or SITE element|)
  elsehandle NONE
    -- If no equipment are found, and we're at a ZONE try collecting for SITE
    if !coll.size().eq(0) and !level.eq(|ZONE|) then
      !!alert.message(|No equipment found in current ZONE, so whole SITE will be searched|)
      VAR !coll COLL ALL EQUIP FOR SITE
      !level = |SITE|
    endif
    -- Update the title paragraph gadget
    !this.title.val = |Available Equipments below | & !level
    -- Evaluate the fullnames of the equis and display the information
    VAR !name EVAL FLNN FOR ALL FROM !coll
    !this.equip.dtext = !name
    !this.equip.rtext = !coll
    -- Collect the nozzles
    !this.collectNozzles()
  endhandle
endmethod

-----
-- Method .collectNozzles() - For the selected EQUI, collect all the nozzles --
-----
define method .collectNozzles()
  -- Get the selected EQUI element
  !equipRef = !this.equip.selection().dbref()
  if !equipRef.unset() then
    -- If the element is unset, then clear the nozzle list
    !this.nozzleList.clear()
  else
    -- Perform a PML2 style collection for the nozzles
    !nozzColl = object COLLECTION()

```

```

!nozzColl.type('NOZZ')
!nozzColl.scope(!equipRef)
!results = !nozzColl.results()
!this.nozzleList.dtext = !results.evaluate(object block ('!results[!evalIndex].flnn'))
!this.nozzleList.rtext = !results.evaluate(object block ('!results[!evalIndex].string()'))
-- Check the nozzles and update the results
!this.checkNozzles()
!this.clear()
!this.updateAtt(1)
!this.setDrawlist()
!this.enableClip()
!this.highlight()
!this.tagged.clear()
do !n index !this.nozzleList.dtext
    !this.tagged[!n] = FALSE
enddo
endif
endmethod

-----
-- Method .setEquip(GADGET, STRING) - Open callback on combo gadget to check user entry --
-----

define method .setEquip(!gad is gadget, !event is STRING)
-- If the user has typed into the gadget
if !event.eq('VALIDATE') then
    !userInput = !this.equip.displayText()
    -- Loop through available equipments and choice the nearest match
    do !n index !this.equip.dtext
        !chrs = !userInput.length()
        !test = !this.equip.dtext[!n].upcase().substring(1, !chrs)
        if !userInput.upcase().eq(!test) then
            !this.equip.val = !n
            break
        endif
    enddo
endif
endmethod

-- Recollect the nozzles on the newly selected equipment
!this.collectNozzles()
endmethod

-----
-- Method .checkNozzles() - Check the collected nozzles and display the results --
-----

define method .checkNozzles()
if !this.nozzleList.rtext.set() then
    -- Loop through the collected nozzles
    do !n index !this.nozzleList.rtext
        !nozz = !this.nozzleList.rtext[!n].dbref()
        -- set the default result
        do !m from 2 to 4
            !result[!m] = |N/A|
        enddo
        -- Check 1: is the connection valid
        if !nozz.cref.unset().or(!nozz.cref.badref()) then
            !result[1] = |Check|
        else
            !result[1] = |OK|
            !end = |t|
            if !nozz.cref.href.eq(!nozz) then
                !end = |h|
            endif
            -- Check 2: is the nozzle and the same position as the attached
            if !nozz.pos.wrt( /* ).eq(!nozz.cref.attribute(!end & |pos|).wrt( /* )) then
                !result[2] = |OK|
            endif

            -- Check 3: is the nozzle and the same direction as the attached
            if !nozz.pdir[1].wrt( /* ).eq(!nozz.cref.attribute(!end & |dir|).wrt( /* )) then
                !result[3] = |OK|
            endif
            -- Check 4: is the nozzle and the same size as the attached
            if !nozz.cpar[1].eq(!nozz.cref.attribute(!end & |bore|).real()) then
                !result[4] = |OK|
            endif
        endif
        -- Record the check results for this nozzle
        !nozzleInfo[!n][1] = !nozz.flnn
        !nozzleInfo[!n].appendArray(!result)
    enddo
    !this.highlight = !nozzleInfo
    -- Apply the results back to the list gadget
    !rtext = !this.nozzleList.rtext

```

```

        !this.nozzleList.setRows(!nozzleInfo)
        !this.nozzleList.rtext = !rtext
    endif
endmethod

```

```

-----
-- Method .updateAtt(REAL) - Check the collected nozzles and display the results      --
-----

```

```

define method .updateAtt(!flag is REAL)
-- Get the selected piece of equipment and the available attributes
!equip = !this.equip.selection().dbref()
!availAtts = !equip.attributes()
-- Update the textpane title
!this.atta.tag = !equip.flnn & ' Attributes'
!rows = !this.atta.val
-- Loop through the rows of the textpane to extract and use the information
!out = ARRAY()
do !n index !rows
    -- Split the line on a "-"
    !split = !rows[!n].split('-')
    !attrib = !split[1].trim()
    -- Evaluate the available attributes so they are the same string length as the entered
    !block = object block ('!availAtts[!evalIndex].upcase().substring(1, !attrib.length())')
    !avail = !availAtts.evaluate(!block)
    -- If the attribute can be found, then use it
    if !avail.findfirst(!attrib.upcase()).set() then
        if !flag.eq(1) then
            -- If the flag = 1 then update the textpane with the current attribute value
            !value = !equip.attribute(!availAtts[!avail.findfirst(!attrib.upcase())])
            !out.append(!attrib & | - | & !value)
        elseif !flag.eq(2) then
            -- If the flag = 2 then assign the value to the attribute
            !val = !split[2].trim()
            !equip.attribute(!availAtts[!avail.findfirst(!attrib.upcase())]).assign(!val)
            !out.append(!attrib & | - | & !val)
        endif
    endif
enddo
-- Display the updated attribute list
!this.atta.val = !out
Endmethod

```

```

-----
-- Method .setDrawlist(REAL) - Add the select equipment to the drawlist              --
-----

```

```

define method .setDrawlist()
-- Get the selected equipment and drawlist associated with the view
!equip = !this.equip.selection().dbref()
!drawlist = !!gphDrawlists.drawlist(!this.drawlist)
!drawlist.holes(TRUE)
-- Clear the draw, add the equi and set the limits
!drawlist.removeall()
!drawlist.add(!equip)
!!gphViews.limits(!this.volumeView, !equip)
Endmethod

```

```

-----
-- Method .setDrawlist(REAL) - Add the select equipment to the drawlist              --
-----

```

```

define method .colourpick(!colour is ANY)
-- Based on the colour button pressed, set the colour
!col = !colour.string()

if !col.eq('A') then
    !this.col = 1
    !this.colourpick.visible = TRUE
elseif !col.eq('B') then
    !this.col = 2
    !this.colourpick.visible = TRUE
elseif !col.eq('C') then
    !this.col = 3
    !this.colourpick.visible = TRUE
elseif !col.eq('D') then
    !this.col = 4
    !this.colourpick.visible = TRUE
else
    if !this.col.eq(1) then

```

```

        !this.butt1.background = !col.real()
    elseif !this.col.eq(2) then
        !this.butt2.background = !col.real()
    elseif !this.col.eq(3) then
        !this.butt3.background = !col.real()
    elseif !this.col.eq(4) then
        !this.butt4.background = !col.real()
    endif
    !this.colourpick.visible = FALSE
    -- Rehighlight with the new colours
    !this.highlight()
endif
endmethod

-----
-- Method .highlight() - Highlight the equipment and nozzles --
-----

define method .highlight()
    -- Get the selected equipment
    !equip = !this.equip.selection().dbref()
    -- If highlighting is required
    if !this.hlNozzBut.val then
        -- Highlight the equipment
        !gphDrawlists.drawlists[!this.drawlist].highlight(!equip,!this.butt1.background)
        -- Update the icons
        !this.hlNozzPix.AddPixmap(!PML.GetPathName('nozzle-16.png'))
        !this.hlNozzBut.tag = |Unhighlight Nozzles|
        -- Show then hidden frame
        !this.colour.visible = TRUE
        -- Loop through any displayed nozzles
        if !this.nozzleList.rtext.set() then
            -- Highlight the nozzles based on the check results
            !nozz = !this.highlight
            do !I index !nozz
                !nozzle = !this.nozzleList.rtext[!I].dbref()
                if !nozz[!I][2].eq(|OK|) then
                    !col = !this.butt2.background
                elseif !nozz[!I][2].eq(|Check|) then
                    !col = !this.butt3.background
                endif
                if !nozz[!I][3].eq(|Check|) or !nozz[!I][4].eq(|Check|) or !nozz[!I][5].eq(|Check|) then
                    !col = !this.butt4.background
                endif
                -- Highlight the nozzle
                !gphDrawlists.drawlists[!this.drawlist].highlight(!nozzle,!col)
            enddo
        endif
    else
        -- Reset the icons
        !this.hlNozzPix.AddPixmap(!PML.GetPathName('nozzle-16.png'))
        !this.hlNozzBut.tag = |Highlight Nozzles|
        -- Hide the frame
        !this.colour.visible = FALSE
        !this.colour.expanded = FALSE
        -- Unhighlight everything
        !gphDrawlists.drawlists[!this.drawlist].unhighlight(!equip)
        if !this.nozzleList.rtext.set() then
            do !i index !this.nozzleList.rtext
                !gphDrawlists.drawlists[!this.drawlist].unhighlight(!this.nozzleList.rtext[!i].dbref())
            enddo
        endif
    endif
endmethod

-----
-- Method .slide() - Increase the size of the clip box based on the slider --
-----

define method .slide()
    -- Get the value of the slider
    !value = !this.slide.val
    -- Update the limits if required
    if !this.incl.val then
        !limits = !this.limits
        !modlimit[1] = !limits[1] - !value
        !modlimit[2] = !limits[2] + !value
        !modlimit[3] = !limits[3] - !value
        !modlimit[4] = !limits[4] + !value
        !modlimit[5] = !limits[5] - !value
        !modlimit[6] = !limits[6] + !value
        !this.volumeView.limits = !modlimit
    endif
endmethod

```

```

-- Update the clip box and refresh the view
!this.volumeView.clipBoxXlen = !this.clipbox.box.xlength + !value
!this.volumeView.clipBoxYlen = !this.clipbox.box.ylength + !value
!this.volumeView.clipBoxZlen = !this.clipbox.box.zlength + !value
!this.volumeView.refresh()
endmethod

-----
-- Method .enableClip() - Apply the clipbox to the view --
-----

define method .enableClip()
-- Get the drawlist and find the connected elements
!drawlist = !!gphDrawlists.drawlist(!this.drawlist)
!connectNozz = ARRAY()
do !n index !this.nozzleList.rtext
    !nozz = !this.nozzleList.rtext[!n]
    if !nozz.dbref().cref.unset().not().and(!nozz.dbref().cref.badref().not()) then
        !connectNozz.append(!nozz.dbref().cref)
    endif
enddo
-- Get the volume of the equipment. Set the clipbox to the size of the volume
!volume = object volume(!this.equip.selection().dbref())
!this.clipbox.box = !volume.box()
-- If the clip is turned on
if !this.clipBut.val then
    -- Update the icons
    !this.clipBut.tag = |Remove Connected and Disable Clipbox...|
    !this.clipPix.addPixmap(!pml.getPathName(|nozzle-16.png|))
    !this.limitslide.visible = TRUE
    -- Loop through connected and add them to the drawlist
    do !n index !connectNozz
        !drawlist.add(!connectNozz[!n])
    enddo
    -- Update the clip box and apply it
    !this.limits = !this.volumeView.limits
    !this.clipbox.active = FALSE
    !this.clipbox.set()
    !this.clipbox.active = TRUE
    !this.volumeView.clipping = TRUE
    !this.slide()
else
    -- Update the icons
    !this.clipBut.tag = |Add Connected and Enable Clipbox...|
    !this.clipPix.addPixmap(!pml.getPathName(|nozzle-16.png|))
    !this.limitslide.visible = FALSE
    !this.limitslide.expanded = FALSE
    -- Remove the connected elements from the drawlist
    do !n index !connectNozz
        !drawlist.remove(!connectNozz[!n])
    enddo
    !this.clipbox.active = FALSE
    !this.volumeView.clipping = FALSE
endif
endmethod

-----
-- Method .tag(GADGET) - Apply the clipbox to the view --
-----

define method .tag(!gad is GADGET)
-- If the gadget is a single tag - only tag the selected
!check1 = !gad.tag.upcase().eq(|TAG SELECTED NOZZLE|)
!check2 = !gad.tag.upcase().eq(|UNTAG SELECTED NOZZLE|)
if !check1.or(!check2) then
    !start = !this.nozzleList.val
    !finish = !this.nozzleList.val
else
    !start = 1
    !finish = !this.nozzleList.dtext.size()
endif
-- If tagging, loop through the nozzles and tag
if !gad.val then
    do !n from !start to !finish
        if !this.tagged[!n].eq(FALSE) then
            !nozzname = !this.nozzleList.rtext[!n].dbref().flnn
            !nozzpos = !this.nozzleList.rtext[!n].dbref().pos
            !num = 1500 + !n
            AID TEXT NUMBER $!num '$!nozzname' AT $!nozzpos
            !this.tagged[!n] = TRUE
        endif
    enddo
else

```

```

-- else, loop through and untag
do !n from !start to !finish
    !num = 1500 + !n
    AID CLEAR text $!num
    handle ANY
endhandle
!this.tagged[!n] = FALSE
enddo
endif
-- Check if all nozzles have been tagged, if so - update the icons
!testTagged = !this.tagged
!testTagged.unique()
if !testtagged.size().eq(1).and(!testtagged[1].eq(TRUE)) then
    !this.tagNozzlesBut.val = TRUE
    !this.tagNozzlesBut.tag = |Untag All Nozzles|
    !this.tagNozzlesPix.addPixmap(!pml.getPathName(|draft_lab_06.png|))
else
    !this.tagNozzlesBut.val = FALSE
    !this.tagNozzlesBut.tag = |Tag All Nozzles|
    !this.tagNozzlesPix.addPixmap(!pml.getPathName(|draft_lab_01.png|))
endif
-- Re-check
!this.check()
endmethod

-----
-- Method .check() - Apply the clipbox to the view
-----
define method .check()
    -- If the selected is tagged, update the icons and tag
    !check = !this.tagged[!this.nozzleList.val]
    if !check then
        !this.tagNozzBut.val = TRUE
        !this.tagNozzBut.tag = |Untag Selected Nozzle|
        !this.tagNozzPix.addPixmap(!pml.getPathName(|draft_lab_06.png|))
    else
        !this.tagNozzBut.val = FALSE
        !this.tagNozzBut.tag = |Tag Selected Nozzle|
        !this.tagNozzPix.addPixmap(!pml.getPathName(|draft_lab_01.png|))
    endif
endmethod

-----
-- Method .updateRange() - Update the slider range based on user entered values
-----
define method .updateRange()
    !range[1] = !this.minslide.val
    !range[2] = !this.maxslide.val
    !range[3] = 100
    !this.slide.range = !range
    !this.slide.refresh()
endmethod

-----
-- Method .clear() - Tidy up and reset the form
-----
define method .clear()
    do !n index !this.nozzleList.rtext
        !num = 1500 + !n
        AID CLEAR text $!num
        handle ANY
    endhandle
    enddo
    !this.tagNozzBut.val = FALSE
    !this.tagNozzBut.tag = |Tag Selected Nozzle|
    !this.tagNozzPix.addPixmap(!pml.getPathName(|draft_lab_06.png|))
    !this.tagNozzlesBut.val = FALSE
    !this.tagNozzlesBut.tag = |Tag All Nozzles|
    !this.tagNozzlesPix.addPixmap(!pml.getPathName(|draft_lab_01.png|))
endmethod

-----
-- End of Form definition and methods
-----
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
-----

```

## Appendix B7 - Example c2ex6.pmlfrm

```
-----
--
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
--
-- File: c2ex6.pmlfrm
--
-- Description:
-- Example form solution to Exercise 6
--
-- Supplied to support AVEVA training course TM1881 - PML: Form Design
--
-----
-- Form definition
-----

setup form !!c2ex6 dialog resizable

-- Set the form title and initialisation call
!this.formTitle = |Equipment Checker|
!this.initcall = |!this.init()|
!this.quitcall = |!this.tidy()|

-- Create a MENU object for use as a context menu on the list gadget
!this.newMenu(|popupMenu|)
!popupCall = '!!CE = !this.nozzleList.selection().dbref()'
!this.popupMenu.add('CALLBACK', 'Go to Nozzle', !popupCall)

-- Define the gadgets at the top of the form
button .update linklabel |Update| call |!this.init()| width 5
para .title at xmax ymin anchor t+l+r text |Available Equipments below | width 34
line .line at xmin.update ymax anchor t+l+r horizontal width 42

!buttPos = |xmax - size ymax anchor b+r|
!anch1 = |anchor t+l+r |
!anch2 = |anchor b+l+r|

-- Define the gadgets to choose the equipments from
button .pick at xmin.update ymax+0.2 pixmap width 33 height 32
combo .equip at xmax+0.2 ymin |Select an Equipment| tagwidth 14 $!anch1 width 22
list .nozzleList at xmin.update ymax+0.5 anchor all width 40 length 5
button .refresh linklabel |Refresh Checks| at $!buttPos width 9.6

-- Define the gadgets to allow the attributes to be altered
!tag = |Equipment Attributes|
textpane .atta |$!tag| at xmin.nozzleList ymax-0.5 $!anch2 width 42 height 3.5
button .updateAtta linklabel |Update Attributes| at $!buttPos width 10.3

exit

-----
-- Constructor Method - Set the images and callbacks on the form
-----

define method .c2ex6(
-- Set the titles and context menu on the list
!title = |Nozzles/Connected?/Attached?/Aligned?/Size?|
!this.nozzleList.setHeadings(!title.split(|/|))
!this.nozzleList.setpopup(!this.popupMenu)
-- Pre-fill-in some attributes to be edited
!info[1] = 'Description - Unset'
!info[2] = 'Function - Unset'
!info[3] = 'Purpose - Unset'
!this.atta.val = !info
-- Set the gadget callbacks
!this.pick.callback = |!this.pick()|
!this.equip.callback = |!this.setEquip()|
!this.refresh.callback = |!this.checkNozzles()|
!this.updateAtta.callback = |!this.updateAtt(2)|
-- Set the icon and tooltip of the pixmap button
!this.pick.addPixmap(!pml.getPathName(|onepick.png|))
!this.pick.setToolTip(|Identify Equipment from 3D View|)
endmethod

--(Continues on next page)
```



```

-----
-- Initialisation Method - Collect all equi the current element and display nozzles --
-----
define method .init()
    !this.collectEquipment(!!ce)
endmethod

-----
-- Quit Call Method - Tidy any activate pick events --
-----
define method .tidy()
    -- Clear the any existing pick
    !!edgCntrl.remove(|Identify Equipment|)
endmethod

-----
-- Method .collectEquipment(DBREF) - Collect all equi for level and display nozzles --
-----
define method .collectEquipment(!item is DBREF)
    -- Loop up to find a SITE or ZONE
    !allowableTypes = |ZONE SITE WORL|
    do
        break if !allowableTypes.split().findFirst(!item.type).set()
        !item = !item.owner
    enddo
    -- If we have found a SITE or ZONE, continue
    if !allowableTypes.split().findFirst(!item.type).neq(3) then
        -- Collect the equipment using PML 1 style collection syntax
        VAR !coll COLL ALL EQUIP FOR $!item
        -- If no equipment are found, offer the chance to collect for the owner
        if !coll.unset() then
            !message = |No equipment found for | & !item.type & |, |
            !message = !message & |do you wish to search the | & !item.owner.type & |?|
            if !!alert.confirm(!message).eq(|YES|) then
                !this.collectEquipment(!item.owner)
                return
            endif
        endif
        -- Update the title paragraph gadget
        !this.title.val = |Available Equipments below | & !item.type & | | & !item.flnn
        -- Evaluate the fullnames of the equis and display the information
        VAR !name EVAL FLNN FOR ALL FROM !coll
        !this.equip.dtext = !name
        !this.equip.rtext = !coll
        -- Collect the nozzles
        !this.collectNozzles()
    endif
endmethod

-----
-- Method .collectNozzles() - For the selected EQUI, collect all the nozzles --
-----
define method .collectNozzles()
    -- Get the selected EQUI element
    !equipRef = !this.equip.selection().dbref()
    if !equipRef.unset() then
        -- If the element is unset, then clear the nozzle list
        !this.nozzleList.clear()
    else
        -- Perform a PML2 style collection for the nozzles
        !nozzColl = object COLLECTION()
        !nozzColl.type('NOZZ')
        !nozzColl.scope(!equipRef)
        !results = !nozzColl.results()
        !this.nozzleList.dtext = !results.evaluate(object block ('!results[!evalIndex].flnn'))
        !this.nozzleList.rtext = !results.evaluate(object block ('!results[!evalIndex].string()'))
        -- Check the nozzles and update the results
        !this.checkNozzles()
        !this.updateAtt(1)
    endif
endmethod

-----
-- Method .setEquip(GADGET, STRING) - Open callback on combo gadget to check user entry --
-----
define method .setEquip(!gad is gadget, !event is STRING)
    -- If the user has typed into the gadget
    if !event.eq('VALIDATE') then
        !userInput = !this.equip.displayText()

        --(Continues on next page)
    end
end

```

```

-- Loop through available equipments and choice the nearest match
do !n index !this.equip.dtext
!chrs = !userInput.length()
!test = !this.equip.dtext[!n].upcase().substring(1, !chrs)
if !userInput.upcase().eq(!test) then
!this.equip.val = !n
break
endif
enddo
endif
-- Recollect the nozzles on the newly selected equipment
!this.collectNozzles()
endmethod

-----
-- Method .checkNozzles() - Check the collected nozzles and display the results --
-----

define method .checkNozzles()
if !this.nozzleList.rtext.set() then
-- Loop through the collected nozzles
do !n index !this.nozzleList.rtext
!nozz = !this.nozzleList.rtext[!n].dbref()
-- set the default result
do !m from 2 to 4
!result[!m] = |N/A|
enddo
-- Check 1: is the connection valid
if !nozz.cref.unset().or(!nozz.cref.badref()) then
!result[1] = |Check|
else
!result[1] = |OK|
!end = |t|
if !nozz.cref.href.eq(!nozz) then
!end = |h|
endif
-- Check 2: is the nozzle and the same position as the attached
if !nozz.pos.wrt( /* ).eq(!nozz.cref.attribute(!end & |pos|).wrt( /* )) then
!result[2] = |OK|
endif
-- Check 3: is the nozzle and the same direction as the attached
if !nozz.pdir[1].wrt( /* ).eq(!nozz.cref.attribute(!end & |dir|).wrt( /* )) then
!result[3] = |OK|
endif
-- Check 4: is the nozzle and the same size as the attached
if !nozz.cpar[1].eq(!nozz.cref.attribute(!end & |bore|.real())) then
!result[4] = |OK|
endif
endif
-- Record the check results for this nozzle
!nozzleInfo[!n][1] = !nozz.flpn
!nozzleInfo[!n].appendArray(!result)
enddo
-- Apply the results back to the list gadget
!rtext = !this.nozzleList.rtext
!this.nozzleList.setRows(!nozzleInfo)
!this.nozzleList.rtext = !rtext
endif
endmethod

-----
-- Method .updateAtt(REAL) - Check the collected nozzles and display the results --
-----

define method .updateAtt(!flag is REAL)
-- Get the selected piece of equipment and the available attributes
!equip = !this.equip.selection().dbref()
!availAtts = !equip.attributes()
-- Update the textpane title
!this.atta.tag = !equip.flpn & ' Attributes'
!rows = !this.atta.val
-- Loop through the rows of the textpane to extract and use the information
!out = ARRAY()
do !n index !rows
-- Split the line on a "-"
!split = !rows[!n].split('-')
!attrib = !split[1].trim()
-- Evaluate the available attributes so they are the same string length as the entered
!block = object block ('!availAtts[!evalIndex].upcase().substring(1, !attrib.length())')
!avail = !availAtts.evaluate(!block)
--(Continues on next page)

-- If the attribute can be found, then use it
if !avail.findfirst(!attrib.upcase()).set() then

```

```

if !flag.eq(1) then
    -- If the flag = 1 then update the textpane with the current attribute value
    !value = !equip.attribute(!availAtts[!avail.findfirst(!attrib.upcase())])
    !out.append(!attrib & | - | & !value)
elseif !flag.eq(2) then
    -- If the flag = 2 then assign the value to the attribute
    !val = !split[2].trim()
    !equip.attribute(!availAtts[!avail.findfirst(!attrib.upcase())]).assign(!val)
    !out.append(!attrib & | - | & !val)
endif
endif
enddo
-- Display the updated attribute list
!this.atta.val = !out
endmethod
-----
-- Method .pick() - Setup and activate the pick event
-----
define method .pick()
    -- Clear the any existing pick
    !!edgCtrl.remove(|Identify Equipment|)
    -- Declare the EDGPACKET object
    !packet = object EDGPACKET()
    !packet.elementPick(|Identify Equipment or Nozzle <Esc> to finish|)
    !packet.description = |Identify Equipment|
    !packet.action = ||!c2ex6.pickProcess(!this.return[1].item)|
    -- Add the packet to the system and activate the pick
    !!edgCtrl.add(!packet)
endmethod
-----
-- Method .pickProcess(DBREF) - Process the identified equipment
-----
define method .pickProcess(!item is DBREF)
    !allowableTypes = |EQUI NOZZ WORL|
    -- Loop up to find an EQUI/NOZZ (or the world)
    do
        break if !allowableTypes.split().findFirst(!item.type).set()
        !item = !item.owner
    enddo
    -- If we have found an EQUI, proceed...
    if !item.type.eq(|EQUI|).or(!item.type.eq(|NOZZ|)) then
        -- Find the item in the list
        if !item.type.eq(|EQUI|) then
            !val = !this.equip.rtext.findfirst(!item.string())
        else
            !expression = object EXPRESSION(|REFNO OF EQUI|)
            !equi = !expression.evaluate(!item)
            !val = !this.equip.rtext.findfirst(!equi.string())
        endif
        if !val.set() then
            -- If the equipment can be found in the list, pick it
            !this.equip.val = !val
            !this.collectNozzles()
            -- If a nozzle has been picked, ensure it is selected
            if !item.type.eq(|NOZZ|) then
                !val = !this.nozzleList.rtext.findfirst(!item.string())
                !this.nozzleList.val = !val
            endif
        else
            -- If not, offer the chance to recollect
            !message = |Identified equipment not in list. Do you wish to re-collect?|
            if !!alert.confirm(!message).eq(|YES|) then
                -- Recollect for the owner of the identified equipment
                !this.collectEquipment(!item.owner)
            endif
        endif
    endif
endmethod
-----
-- End of Form definition and methods
-----
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
-----

```

## Appendix B8 - Example traExampleExplorer.pmlfrm

```

--
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
--
-- File:          traExampleExplorer.pmlfrm
--
-- Description:
--   Form to demonstrate the use of a NETEXPLORER PML.NET Control inside a CONTAINER
--
--   Supplied to support AVEVA training course TM1881 - PML: Form Design
--
-----
-- Form definition
-----

setup form !!traExampleExplorer dialog docking

-- Load the required .dll for the explorer .NET gadget
import 'ExplorerAddin'
handle ANY
-- Handle all errors, incase its already been loaded
endhandle
using namespace 'Aveva.Core.Presentation'

-- Set the form title
!this.formTitle = 'Example .NET Explorer'

-- Create a popup menu object
!this.newMenu(|explorerPopup|)
!this.explorerPopup.add( 'CALLBACK', 'popup', '!this.popup()' )

para      .pmlTitle at x 0.2      ymax text |Standard PML gadgets|
line      .pmlLine  at xmin - 0.1 ymax-0.5 anchor l+t+r horizontal wid 35 hei 0.7

-- Define the functionality at the top of the form
toggle .track      |Track CE|      at xmin + 2 ymax anchor t+l
button .select linklabel |Find CE >>| at xmax ymin anchor t+r width 8
button .reset linklabel |Reset to CE >>| at xmax ymin anchor t+r width 10

para      .netTitle at xmin.pmlTitle ymax text |.NET Container|
line      .netLine  at xmin.pmlLine ymax-0.5 anchor l+t+r horizontal wid 35 hei 0.7

-- Define the container that will hold the NETEXPLORER
!size = |wid 33 hei 15|
container .netFrame NOBOX PMLNETCONTROL '' at xmin+1 ymax anchor all $!size

line .line at xmin.netLine ymax+0.5 anchor b+l+r horizontal width 35
para .footer at xcen - 0.5 * size ymax anchor b text |AVEVA Training| width 11

-- Store the explorer control as a form member for future reference
member .explorer is PMLEXPLORERCONTROL
member .element is DBREF
exit
-- End of form definition
--
-----
-- Constructor Method - Setup the form when it is loaded
-----

define method .traExampleExplorer()

-- Apply the callbacks to the PML gadgets
!this.select.callback = !!this.explorer.selectElement(!!ce.name)|
!this.track.callback  = !!this.explorer.setFollowCe(!this.track.val)|
!this.reset.callback  = !!this.explorer.resetRoot(!!ce.name)|

-- Specify the namespace before using the .NET gadget
using namespace 'Aveva.Core.Presentation'

-- Create an instance of the control
!this.explorer = object PMLEXPLORERCONTROL()
!this.netFrame.control = !this.explorer.handle()
-- Register for the OnPopup event
!this.explorer.addeventhandler('OnPopup', !this, 'rightClickExplorer')
--(Continues on next page)

-- Use methods on Explorer C# control
!this.explorer.initialise('/*', '')
endmethod
-- End of Constructor Method
--
-----

```

```
-- Method .rightClickExplorer(ARRAY) - Show context menu on explorer      --
-----
define method .rightClickExplorer(!data is ARRAY)
  !this.netFrame.popup = !this.explorerPopup
  !this.netFrame.showPopup(!data[0], !data[1])
  !this.element = !data[2].dbref()
endmethod
-- End of Method .rightClickExplorer(ARRAY)
--
-----
-- Method .popup() - Query the name of the selected element              --
-----
define method .popup()
  q var !this.element.name
endmethod
-- End of Method .popup()
--
-----
-- End of Form definition and methods                                     --
-----
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited            --
-----
```

Copia para EE AA

## Appendix B9 - Example traExampleGridControl.pmlfrm

```
--
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited
--
-- File:          traExampleGridControl.pmlfrm
--
-- Description:
--   Form to demonstrate the use of a Grid Control PML.NET Control inside a CONTAINER
--
--   Supplied to support AVEVA training course TM1881 - PML: Form Design
--
-----
-- Form definition
-----

setup form !!traExampleGridControl dialog docking

-- Load the required .dll for the explorer .NET gadget
import 'GridControl'
handle ANY
  -- Handle all errors, incase its already been loaded
endhandle
using namespace 'Aveva.Core.Presentation'

-- Set the form title and the initialisation call
!this.formTitle = |Example .NET Grid Control|
!this.initcall = |!this.init()|

-- Create a popup menu object
!this.newMenu(|gridPopup|)
!this.gridPopup.add('CALLBACK', 'Add to 3D View', '!this.addToThreeDview()')
!this.gridPopup.add('CALLBACK', 'Save to Excel...', '!this.savToExcel()')
!this.gridPopup.add('CALLBACK', 'Import from Excel...', '!this.loadFromExcel()')

-- Specify the container that will hold the grid control .NET gadget
container .gridFrame NOBOX PMLNETCONTROL 'grid' anchor all width 60 height 20

line .line at xmin ymax+0.5 anchor b+l+r horizontal width 60
para .footer at xcen - 0.5 * size ymax anchor b text |AVEVA Training| width 11

member .grid is NETGRIDCONTROL
member .elements is ARRAY

exit
-- End of form definition
--
-----
-- Constructor Method - Setup the form when it is loaded
-----

define method .traExampleGridControl()

  -- Specify the namespace before using the .NET gadget
  using namespace 'Aveva.Core.Presentation'

  -- Create an instance of the control
  !this.grid = object NetGridControl()
  !this.gridFrame.control = !this.grid.handle()

  -- Apply the event handlers
  !this.grid.addeventhandler('OnPopup', !this, 'rightClickGrid')
  !this.grid.addeventhandler('AfterSelectChange', !this, 'afterSelectChange')
  !this.grid.addeventhandler('BeforeCellUpdate', !this, 'beforeCellUpdate')
endmethod
-- End of Constructor Method
--
-----
-- Initialisation Method - Setup the Grid Control on the form
-----

define method .init()

  -- Specify the namespace before using the .NET gadget
  using namespace 'Aveva.Core.Presentation'
  -- Create headings
  !headings = |Name Type Owner Description|
  --(Continues on next page)
```

```

-- Create model items for population of grid
var !data collect all EQUIP
var !data append collect all PIPES

-- Bind data to grid
!nds = object NETDATASOURCE('Grid Control Example', !headings.split(), !data)
!this.grid.bindToDataSource(!nds)

-- Set grid parameters
!this.grid.columnExcelFilter(TRUE)
!this.grid.setNameColumnImage()
!this.grid.outlookGroupStyle(TRUE)
!this.grid.fixedHeaders(FALSE)
!this.grid.fixedRows(FALSE)
!this.grid.columnSummaries(TRUE)
!this.grid.autoFitColumns()
--!this.grid.editableGrid(TRUE)
--!this.grid.setEditableColumn(4,TRUE)
--!this.grid.setColumnColor(4, 'white')
endmethod
-- End of Initialisation Method
--
-----
-- Method .rightClickGrid(ARRAY) - Show the context menu on the control --
-----
define method .rightClickGrid(!data is ARRAY)
!this.gridFrame.popup = !this.gridPopup
!this.gridFrame.showPopup(!data[0], !data[1])
!this.elements = !data[2]
endmethod
-- End of Initialisation Method
--
-----
-- Method .addToThreeDView() - Adds the selected elements to the drawlist --
-----
define method .addToThreeDView()
do !element values !this.elements
add $!element
enddo
endmethod
-- End of Method .addToThreeDView()
--
-----
-- Method .saveToExcel() - Save the grid to excel via the file browser --
-----
define method .saveToExcel()

-- Ensure the correct .dll is loaded
import 'PMLFileBrowser'
handle ANY
endhandle

-- Specify the namespace before using the .NET gadget
using namespace 'Aveva.Core.Presentation'

-- Show the browser form and based on the file, save the grid
!browser = object PMLFILEBROWSER('SAVE')
!browser.show('C:\', 'Example.xls', 'Save to Excel', false, 'Excel Files|*.xls|,1)
!this.grid.saveGridToExcel(!browser.file())
endmethod
-- End of Method .saveToExcel()
--
-----
-- Method .loadFromExcel() - Load the grid from excel via the file browser --
-----
define method .loadFromExcel()

-- Ensure the correct .dll is loaded
import 'PMLFileBrowser'
handle ANY
endhandle

-- Specify the namespace before using the .NET gadget
using namespace 'Aveva.Core.Presentation'

--(Continues on next page)

```

```

-- Show the browser form and based on the file, fill the grid
!browser = object PMLFILEBROWSER('OPEN')
!browser.show('C:\', '', 'Load Grid from Excel', true, 'Excel Documents\*.xls', 1)
!this.grid.clearGrid()
!nds = object NETDATASOURCE('Grid Control Example', !browser.file())
!this.grid.BindToDataSource(!nds)
endmethod
-- End of Method .loadFromExcel()
--
-----
-- Method ..afterSelectChange(ARRAY) - Empty method, ready to be called by the control --
-----
define method .afterSelectChange(!data is ARRAY)

endmethod
-- End of Method .loadFromExcel()
--
-----
-- Method ..beforeCellUpdate(ARRAY) - Perform a DB update with the supplied data --
-----
define method .beforeCellUpdate(!data is ARRAY)
!this.grid.doDabaconCellUpdate(!data)
endmethod
-- End of Method .beforeCellUpdate(ARRAY)
--
-----
-- End of Form definition and methods --
-----
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited --
-----

```

Copia para EEAA



## Appendix B10 - Example c2ex9.pmlfrm

```
--
-- (c) Copyright 2009 to Current Year AVEVA Solutions Limited
--
-- File: c2ex9.pmlfrm
--
-- Description:
-- Example form solution to Exercise 9
--
-- Supplied to support AVEVA training course TM1881 - PML: Form Design
--
--
-- Form definition
--
setup form !!c2ex9 dialog docking

-- Load the required .dll for the explorer .NET gadget
import 'GridControl'
handle ANY
endhandle
import 'ExplorerAddin'
handle ANY
endhandle
using namespace 'Aveva.Core.Presentation'

-- Set the title and initialisation call for the form
!this.formTitle = |Equipment Viewer|
!this.iconTitle = |VIEWER|
!this.callback = |!this.init()|
!this.firstShownCall = |!this.firstShown()|
!this.killingCall = |!this.close()|
!this.formRevision = |1.0|

-- Create a popup menu object
!this.newMenu(|apopup|)
!this.apopup.add('CALLBACK', 'Navigate to Element.', '!ce = !this.selection')
!this.newMenu(|gridPopup|)
!this.gridPopup.add('CALLBACK', 'Navigate To Nozzle.', '!this.showNozzle()')

-- Set up the container gadgets - Notice the use of variables
container .explorerFrame NOBOX PMLNETCONTROL anchor t+l width 35 height 10
!pos = |at xmin.explorerFrame ymax.explorerFrame|
!size = |width 35 height 10|
container .attributeFrame NOBOX PMLNETCONTROL $!pos anchor t+l+b $!size

frame .viewFrame panel at xmax + 0.5 ymin.explorerFrame anchor ALL
view .volumeView VOLUME
width 50 height 20
border off
shading on
isometric 3
exit
exit

-- Specify the user-defined form members
member .attributeGrid is NETGRIDCONTROL
member .designExplorer is PMLEXPLORERCONTROL
member .selection is DBREF
member .drawlist is REAL
exit

-- Constructor Method
define method .c2ex9()
-- Specify Namespace for .Net
using namespace 'Aveva.Core.Presentation'

-- Setup the .Net Controls
!this.designExplorer = object PMLEXPLORERCONTROL()
!this.attributeGrid = object NETGRIDCONTROL()
!this.explorerFrame.control = !this.designExplorer.handle()
!this.attributeFrame.control = !this.attributeGrid.handle()

--(Continues on next page)
```

```

-- add PML event handlers to .Net control
!this.designExplorer.addeventhandler('OnPopup', !this, 'rightClickExplorer')
!this.designExplorer.addeventhandler('OnSelectionChanged', !this, 'updateData')
!this.designExplorer.initialise('/EQUIP', '')
!this.attributeGrid.addeventhandler('OnPopup', !this, 'rightClickGrid')

-- Create a local drawlist within the global object
!this.drawlist = !!gphDrawlists.createDrawList()
endmethod

-----
-- FirstShown Method
-----

define method .firstShown()
-- Add 3D view to view system (this shows the form)
!!gphViews.add(!this.volumeView)

-- add local drawlist to 3D view
!!gphDrawlists.attachView(!this.drawlist, !this.volumeView)
!!gphDrawlists.drawlists[!this.drawlist].holes(TRUE)
endmethod

-----
-- Initialisation Method
-----

define method .init()
-- Setup the Grid Control Gadget
!this.attributeGrid.columnExcelFilter(FALSE)      $* Turn off the filters
!this.attributeGrid.outlookGroupStyle(FALSE)      $* Turn off outlook grouping
!this.attributeGrid.fixedHeaders(FALSE)           $* Turn off fixed headers
!this.attributeGrid.fixedRows(FALSE)              $* Turn off fixed rows
!this.attributeGrid.columnSummaries(FALSE)        $* Turn off summaries
!this.attributeGrid.setLabelVisibility(TRUE)       $* Show Label
!this.attributeGrid.clearGrid()                   $* Clear any existing data
endmethod

-----
-- Close Method
-----

define method .close()
-- On unloading the form, remove drawlist from view and delete it
!!gphDrawlists.detachView(!this.volumeView)
!!gphDrawlists.deleteDrawlist(!this.drawlist)
endmethod

-----
-- Method .updateSystemData(ARRAY) - runs when the explorer is clicked
-----

define method .updateData(!data is ARRAY)

-- Establish the chosen element in the explorer
!this.selection = !data[0].dbref()

-- loop to find an EQUI.
do
break if !this.selection.type.eq(|EQUI|).or(!this.selection.type.eq(|WORL|))
!this.selection = !this.selection.owner
enddo

-- If an EQUI is found, then fill in the information
if !this.selection.type.eq(|EQUI|) then
!this.fillAttributes()
endif

endmethod

-----
-- Method .rightClickExplorer(ARRAY) - runs when the explorer is right clicked
-----

define method .rightClickExplorer(!data is ARRAY)
-- Apply the popup to the container
!this.explorerFrame.popup = !this.apopup

-- Show the popup menu
!this.explorerFrame.showPopup(!data[0], !data[1])
endmethod

-----
-- Method .rightClickGrid(ARRAY) - runs when the grid is right clicked
-----

define method .rightClickGrid(!data is ARRAY)

--(Continues on next page)

```

```

-- Apply the popup to the container
!this.attributeFrame.popup = !this.GridPopup

-- Show the popup menu
!this.attributeFrame.showPopup(!data[0], !data[1])
endmethod

-----
-- Method .showNozzle() - runs when the user selected from the popup --
-----
define method .showNozzle()
    !!ce = !this.attributeGrid.getSelectedrows()[1][1].dbref()
endmethod

-----
-- Method .fillAttributes() - fills the grid will information --
-----
define method .fillAttributes()

    -- Specify Namespace for .Net
    using namespace 'Aveva.Core.Presentation'

    -- Set the Views limits based on the chosen element
    !!gphViews.limits(!this.volumeView, !this.selection)

    -- Update the drawlist by removing the previous and adding the chosen
    !drawlist = !!gphDrawlists.drawlist(!this.drawlist)
    !drawlist.removeall()
    !drawlist.add(!this.selection)

    -- Active the volume view
    !this.volumeView.active = TRUE

    -- Fill in the Grid Control Gadget
    -- Collect all the NOZZs. PML1 syntax used as array of strings needed
    var !data collect all NOZZ for $!this.selection

    -- Attributes required for each nozzle to be filled in
    !attributes = |NAME CPAR[1] CREF|

    -- The titles of the columns for the attributes
    !titles = |Nozzle Size Connection|

    -- Required information passed to a NetDataSource object to compile the info
    !nds = object NETDATASOURCE('Grid', !attributes.split(), !titles.split(), !data)
    !this.attributeGrid.bindToDataSource(!nds)

    -- Set the name column to hold icons of DB elements and autofit the columns
    !this.attributeGrid.setNameColumnImage()
    !this.attributeGrid.autoFitColumns()

    -- Alter the information in the third column (connected)
    -- Define the icons for use in the column
    !error = !!pml.getPathName('ad_t_019.png')
    !ok = !!pml.getPathName('ad_t_018.png')

    -- Collect the current values in column three and loop through them
    !connected = !this.attributeGrid.GetColumn(3)
    do !n index !connected
        !testValue = !this.attributeGrid.getCell(!n, 3)
        !element = !this.attributeGrid.getCell(!n, 1).dbref()
        if !testValue.eq(|Nulref|) then
            $* if found Null element
            !this.attributeGrid.setCellImage(!n, 3, !error) $* apply the missing icon
            !this.attributeGrid.setCellValue(!n, 3, |Check!|) $* change the cell value
            !this.attributeGrid.setCellColor(!n, 3, |white|)
            !!gphDrawlists.drawlists[!this.drawlist].highlight(!element, 2)
        else
            !this.attributeGrid.setCellImage(!n, 3, !ok) $* apply the attached icon
            !!gphDrawlists.drawlists[!this.drawlist].highlight(!element, 5)
        endif
    enddo
endmethod

-----
-- End of Form definition and methods --
-----
-- (c) Copyright 2010 to Current Year AVEVA Solutions Limited --
-----

```

## Appendix B11 - Example appqml.pmlobj

---

### PML addin file

```
name:          PMLTraining
title:         PML Training
showOnMenu:    FALSE
object:        appPML
```

### appqml.obj

```
define object appPML
endobject

define method .modifyMenus()
  !this.utilitiesMenu()
endmethod

define method .modifyForm()
endmethod

define method .utilitiesMenu()
  !menu = object APPMENU('SYSUTIL')
  !menu.add('SEPARATOR')
  !menu.add('FORM', |Calculator|, |c2ex1|)
  !menu.add('MENU', |Equipment Checker|, 'EquipCheck')
  !menu.add('SEPARATOR')
  !!appMenuCntrl.addMenu(!menu, 'EQUI')

  !menu= object APPMENU('EquipCheck')
  !menu.add('FORM', |Exercise 4...|, |c2ex4|)
  !menu.add('FORM', |Exercise 5...|, |c2ex5|)
  !!appMenuCntrl.addMenu(!menu, 'EQUI')
endmethod
```